

URBI Server for Aibo ERS2xx ERS7 Introduction Manual

v 1.0

Jean-Christophe Baillie

January 2005

Contents

| | | |
|----------|---------------------------------------|-----------|
| 1 | Installation | 3 |
| 1.1 | Installing the MS directory | 3 |
| 1.2 | Recompile the server | 3 |
| 2 | Quick start | 4 |
| 2.1 | First contact | 4 |
| 2.2 | Review of some features | 5 |
| 3 | Liburbi | 7 |
| 4 | Devices List | 8 |
| 4.1 | ERS-7 | 9 |
| 4.1.1 | Motors | 9 |
| 4.1.2 | Leds, switches, | 9 |
| 4.1.3 | Sensors | 10 |
| 4.1.4 | Camera | 11 |
| 4.1.5 | Speaker | 11 |
| 4.1.6 | Micro | 11 |
| 4.2 | ERS-210 | 12 |
| 4.2.1 | Motors | 12 |
| 4.2.2 | Leds, switches, | 12 |
| 4.2.3 | Sensors | 13 |
| 4.2.4 | Camera | 13 |
| 4.2.5 | Speaker | 14 |
| 4.2.6 | Micro | 14 |
| 4.3 | ERS-220 | 15 |
| 4.3.1 | Motors | 15 |
| 4.3.2 | Leds, switches, | 15 |
| 4.3.3 | Sensors | 16 |
| 4.3.4 | Camera | 16 |
| 4.3.5 | Speaker | 17 |
| 4.3.6 | Micro | 17 |
| 5 | Default URBLINI | 18 |
| 6 | Default CLIENT.INI | 20 |

Introduction

URBI (Universal Robotic Body Interface) is a scripted language designed to work over a client/server architecture in order to remotely control a robot or, in a broader definition, any kind of device that has actuators and sensors. The main characteristics of URBI, which make it different from other existing solutions are:

- URBI is a low level command language. Motors and sensors are directly read and set. Although complex high level commands and functions can be written with URBI, the raw kernel of the system is low level by essence.
- URBI includes powerful time oriented control mechanisms to chain commands, serialize them or build complex motor trajectories.
- URBI is designed to be independant from both the robot and the client system. It relies on TCP/IP or Inter-Process Communication if the client and the server are both running onboard.
- URBI is designed with a constant care for simplicity. There is no "philosophy" or "complex architecture" to be familiar with. It is understandable in a few minutes and can be used immediately.

URBI Server is released under the GNU General Public License (LICENSE) URBI Language is released under a specific License included in this distribution (LICENSE-URBI-LANGUAGE).

Chapter 1

Installation

You don't have to recompile the server to use it on your Aibo robot. Simply use the MS directory in the 'server-aibo' directory where there is a pre-compiled version available.

1.1 Installing the MS directory

- Prepare your memory stick with the system files for WCONSOLE/memprot/ERSxxx. It should be located in:

```
/usr/local/OPEN_R_SDK/OPEN_R/MS_ERSxxx/WCONSOLE/memprot
```

- copy the OPEN-R directory that you find there in the root of the empty memorystick.
- Then, go to the OPEN-R/SYSTEM/CONF on the memorystick and edit (or create) the WLANCONF.TXT file to suit your network configuration (see the WLANDFLT.TXT for a default setting that you might update).
- Untar the urbiserver.tar.gz file that you downloaded and do a `cd urbiserver` to move to the main directory, called the 'root' directory in the following.
- Then, `cd` to the server-aibo directory in the 'root' and go to the MS directory. Copy (and overwrite if necessary) the content of this MS directory in the root of the memorystick.
- Unmount the memorystick and put it in the robot. It should work. You can telnet the robot on port 54000 to check if everything is OK (you should get a URBI Header at start).

1.2 Recompile the server

If you plan to rebuild the server, simply go into the server-aibo directory in the 'root' directory and type `make install`. This will update the content of the MS directory with the newly compiled server called 'URBI.BIN'. Then, simply proceed through the installation step above to update your server.

Note: there is a kernel part in the 'root' directory. It contains the kernel of the URBI server. You should not modify this part of the code since it might be upgraded later simply by overwriting this directory with the new kernel. If you want to make changes to the kernel or correct bugs, the best is to contact the person responsible of it on sourceforge and see if a new release can be done with your modifications.

Chapter 2

Quick start

The best way to start with URBI is to open a telnet client on the robot, port 54000. You should get something like this:

```
[00139464:notag]
[00139464:start] *****
[00139464:start] URBI Language specif xxx    -    Copyright (C) 2005 JC Baillie
[00139464:start] URBI Kernel version yyy
[00139464:start]
[00139464:start]     URBI Server version zzz for Aibo ERS2xx/ERS7 Robots
[00139464:start]     (C) 2004 Jean-Christophe Baillie
[00139464:start]
[00139464:start] URBI comes with ABSOLUTELY NO WARRANTY;
[00139464:start] This is free software, and you are welcome to redistribute
[00139464:start] it under certain conditions; see GNU GPL for details.
[00139464:start]
[00139464:start] See http://urbi.sourceforge.net for news and updates.
[00139464:start] *****
[00139464:ident] ID: U597766392
```

You can start to enter URBI commands.

2.1 First contact

The command you might want to try is `motoron` to activate your robot motors.
Let's move the head by typing the following command in the telnet client:

```
headPan.val = 15;
headTilt.val = 20;
```

Switch a few LEDs on (these LEDs exist only on ERS7):

```
ledF12.val = 1;
ledF13.val = 0.8;
ledF1.val = 1;
```

What was the head pan value already? Ask for it:

```
headPan.val;
```

It says:

```
[136901543:notag] 15.1030265089
```

Let's play a sound (the wav file is supposed to be on the memorystick root)

```
speaker.play ("welcome.wav");
```

Let's enter a program that will do the ball tracking head:

```
whenever (camera.ballx != -1) {  
  headPan.val = headPan.val + camera.xfov * ( 0.5 - camera.ballx ) &  
  headTilt.val = headTilt.val + camera.yfov * ( 0.5 - camera.bally )  
};
```

2.2 Review of some features

The URBI server receives *commands* from a client and returns *messages* to this client. The normal way of using a URBI controlled robot is to send commands using TCP/IP on the URBI port (54000) and wait for messages in return. A simple telnet client is enough to do that for simple applications, otherwise libraries (liburbi) are available in most programming languages to wrap the TCP/IP sending/receiving job in simple functions.

Any URBI command can be prefixed by a *tag* followed by a colon. If no tag is specified, *notag* is assumed to be the default tag.

Examples:

```
x = 12; // notag  
my_tag: y = x+12; // the tag is 'my_tag'
```

When a command returns a value or when it fails, the URBI server returns a message. The format of a message is the following:

```
[timestamp:tag] message
```

The time stamp is the uptime of the server in milliseconds when the message has been sent. The tag is the tag of the associated command or *notag* if there was no tag specified. The message can be a value (float, string or binary) or a system message prefixed by three stars: *****. Error messages or information messages are system messages.

Here is a typical example of commands with their messages in return:

```
1+1;  
[136901543:notag] 2.0000000000  
  
my_tag:6*6;  
[136904711:my_tag] 36.0000000000  
  
impossible:1/0;  
[136471768:impossible] *** Division by zero  
[136471768:impossible] *** EXPR evaluation failed
```

The ability to tag commands is a key feature of URBI since it allows the client to retrieve the results of specific commands in a flow of messages.

Every sensor, motor or controllable element of the robot is a *device*. It has a device name and can be entirely accessed using this name as prefix. Every device is associated with a set of *fields* and *methods* that can be accessed using the syntax `device.field` or `device.method(...)`. Fields are device specific variables and method are device specific functions. The most useful field to start with is `val` which gives access to a motor angular value, a led illumination or a sensor output.

To know what you can do with your robot, simply check the list of available devices (see at the end) and their fields and methods.

This is already enough to control your robot. But URBI is more than that. You can give complex motor commands with complex trajectories, you can set several commands in series or in parallel, you can do some usual C programming using `while`, `for`, `if`. There are also some advanced features for event catching (`at`, `whenever`).

These features are described in extension in the URBI Language Specification (located in the `doc` directory, at the root of the `urbiserver` directory).

Chapter 3

Liburbi

Using URBI with a telnet is too limited. You need to be able to send commands and receive messages based on tag filter, using a programming language of your choice. This is what liburbi is made for. There is currently a C++ and java version of liburbi if you want to control your robot using C++ or Java and a liburbi-OPENR version if you want to recompile a liburbi-C++ based program to let it run on the robot. See the liburbi documentation for more details.

Chapter 4

Devices List

You can access the list of devices with the `devices` command. Any device can be queried in URBI using the `info` operator:

```
info headPan;  
[04297385:notag] *** description: Head pan  
[04297385:notag] *** device: headPan  
[04297385:notag] *** current value: 28.486434  
[04297385:notag] *** current load: 1.000000  
[04297385:notag] *** rangemin: -91.000000  
[04297385:notag] *** rangemax: 91.000000  
[04297385:notag] *** unit: deg
```

The unit is accessible with the `unit` operator, the min range and max range with the `rangemin` and `rangemax` operators.

The variable `global.nbdevices` contains the number of devices. The variables `device[i]` are the device names.

4.1 ERS-7

4.1.1 Motors

The following devices are joints, with the corresponding range indicated:

| | | |
|----------|--------------------------------|-----------------------------|
| legRF1 | range=[-134.000000,120.000000] | unit=deg : Right fore legJ1 |
| legRF2 | range=[-9.000000,91.000000] | unit=deg : Right fore legJ2 |
| legRF3 | range=[-29.000000,119.000000] | unit=deg : Right fore legJ3 |
| legRH1 | range=[-134.000000,120.000000] | unit=deg : Right hind legJ1 |
| legRH2 | range=[-9.000000,91.000000] | unit=deg : Right hind legJ2 |
| legRH3 | range=[-29.000000,119.000000] | unit=deg : Right hind legJ3 |
| legLF1 | range=[-120.000000,134.000000] | unit=deg : Left fore legJ1 |
| legLF2 | range=[-9.000000,91.000000] | unit=deg : Left fore legJ2 |
| legLF3 | range=[-29.000000,119.000000] | unit=deg : Left fore legJ3 |
| legLH1 | range=[-120.000000,134.000000] | unit=deg : Left hind legJ1 |
| legLH2 | range=[-9.000000,91.000000] | unit=deg : Left hind legJ2 |
| legLH3 | range=[-29.000000,119.000000] | unit=deg : Left hind legJ3 |
| neck | range=[-79.000000,2.000000] | unit=deg : Neck tilt1 |
| headTilt | range=[-16.000000,44.000000] | unit=deg : Neck tilt2 |
| headPan | range=[-91.000000,91.000000] | unit=deg : Head pan |
| tailPan | range=[-59.000000,59.000000] | unit=deg : Tail pan |
| tailTilt | range=[2.000000,63.000000] | unit=deg : Tail tilt |
| mouth | range=[-58.000000,-3.000000] | unit=deg : Mouth |

For all joints, you have the following fields:

- `val` : the value of the joint
- `valn` : the normalized value of the joint between 0 and 1
- `load` : the load of the joint. 0 means “loose”, and 1 means “blocked”. Values in between give intermediary results.
- `PGain` : the P gain of the joint
- `IGain` : the I gain of the joint
- `DGain` : the D gain of the joint
- `PShift` : the P shift of the joint
- `IShift` : the I shift of the joint
- `DShift` : the D shift of the joint

4.1.2 Leds, switches, ...

| | | |
|-------|---------------------------|---------------|
| ledF1 | range=[0.000000,1.000000] | : Face light1 |
| ledF2 | range=[0.000000,1.000000] | : Face light2 |
| ledF3 | range=[0.000000,1.000000] | : Face light3 |
| ledF4 | range=[0.000000,1.000000] | : Face light4 |
| ledF5 | range=[0.000000,1.000000] | : Face light5 |
| ledF6 | range=[0.000000,1.000000] | : Face light6 |

| | | |
|------------|---------------------------|-----------------------------|
| ledF7 | range=[0.000000,1.000000] | : Face light7 |
| ledF8 | range=[0.000000,1.000000] | : Face light8 |
| ledF9 | range=[0.000000,1.000000] | : Face light9 |
| ledF10 | range=[0.000000,1.000000] | : Face light10 |
| ledF11 | range=[0.000000,1.000000] | : Face light11 |
| ledF12 | range=[0.000000,1.000000] | : Face light12 |
| ledF13 | range=[0.000000,1.000000] | : Face light13 |
| ledF14 | range=[0.000000,1.000000] | : Face light14 |
| ledBFC | range=[0.000000,1.000000] | : Back light (front,color) |
| ledBFW | range=[0.000000,1.000000] | : Back light (front,white) |
| ledBMC | range=[0.000000,1.000000] | : Back light (middle,color) |
| ledBMW | range=[0.000000,1.000000] | : Back light (middle,white) |
| ledBRC | range=[0.000000,1.000000] | : Back light (rear,color) |
| ledBRW | range=[0.000000,1.000000] | : Back light (rear,white) |
| ledHC | range=[0.000000,1.000000] | : Head light (color) |
| ledHW | range=[0.000000,1.000000] | : Head light (white) |
| modeB | range=[0.000000,1.000000] | : Mode Indicator (blue) |
| modeG | range=[0.000000,1.000000] | : Mode Indicator (green) |
| modeR | range=[0.000000,1.000000] | : Mode Indicator (red) |
| earL | range=[0.000000,1.000000] | : Left ear |
| earR | range=[0.000000,1.000000] | : Right ear |
| WIFISwitch | range=[0.000000,1.000000] | : Wireless LAN switch |
| ledWIFI | range=[0.000000,1.000000] | : Wireless light |

For all these devices, you have the following fields:

- val : the value of the device
- valn : the normalized value of the device

There is a global “led mode” available on ERS7. You can change it via the global variable `robot.ledMode` (default value is 0). The lights that will be switched on (on the face), and the colors of those lights depends on the mode. Because of this, there is no real one-to-one correspondance between a device name and a physical led on the ERS-7 robot.

4.1.3 Sensors

| | | |
|---------------|------------------------------|------------------------------------|
| pawLF | range=[0.000000,1.000000] | : Left fore leg,paw sensor |
| pawLH | range=[0.000000,1.000000] | : Left hind leg,paw sensor |
| pawRF | range=[0.000000,1.000000] | : Right fore leg,paw sensor |
| pawRH | range=[0.000000,1.000000] | : Right hind leg,paw sensor |
| accelX | range=[-19.613300,19.613300] | : Acceleration sensor (front-back) |
| accelY | range=[-19.613300,19.613300] | : Acceleration sensor (right-left) |
| accelZ | range=[-19.613300,19.613300] | : Acceleration sensor (up-down) |
| chinsensor | range=[0.000000,1.000000] | : Chin sensor |
| backsensorF | range=[0.000000,60.000000] | : Back sensor (front) |
| backsensorM | range=[0.000000,60.000000] | : Back sensor (middle) |
| backsensorR | range=[0.000000,60.000000] | : Back sensor (rear) |
| headsensor | range=[0.000000,35.000000] | : Head sensor |
| distanceChest | range=[19.000000,90.000000] | : Chest distance sensor |
| distanceNear | range=[5.700000,50.000000] | : Head distance sensor (near) |
| distanceFar | range=[20.000000,150.000000] | : Head distance sensor (far) |

For all these devices, you have the following fields:

- `val` : the value of the device
- `valn` : the normalized value of the device

4.1.4 Camera

The camera device on Aibo is called `camera`. The available fields are:

- `val` : the image (binary)
- `shutter` : the camera shutter speed: 1=SLOW (default), 2=MID, 3=FAST
- `gain` : the camera gain: 1=LOW, 2=MID, 3=HIGH (default)
- `wb` : the camera white balance: 1=INDOOR (default), 2=OUTDOOR, 3=FLUO
- `format` : the camera image format: 0=YCbCr 1=jpeg (default)
- `jpegfactor` : the jpeg compression factor (0 to 100). Default=80
- `resolution` : the image resolution: 0:208x160 (default) 1:104x80 2:52x40
- `reconstruct` : reconstruction of the high resolution image(slow): 0:no (default) 1:yes
- `width` : image width
- `height` : image height
- `xfov` : camera x FOV (degrees)
- `yfov` : camera y FOV (degrees)
- `ballx` : normalized X position of the red ball in the image (between 0 and 1) or -1 when there is no ball visible.
- `bally` : normalized Y position of the red ball in the image (between 0 and 1) or -1 when there is no ball visible.

4.1.5 Speaker

The speaker device on Aibo is called `speaker`. The available fields are:

- `val` : the sound to play (binary)
- `playing` : equal 1 when there is a sound playing, 0 otherwise
- `remain` : number of milliseconds of sound to play, 0 when the buffer is empty

There is also a method available:

- `play (file)` : plays the wav file *file* which is stored on the root of the memorystick.

4.1.6 Micro

The micro device on Aibo is called `micro`. The available fields are:

- `val` : contains always a buffer of 2048 bytes of the latest sound heard by the robot.

4.2 ERS-210

4.2.1 Motors

The following devices are joints, with the corresponding range indicated:

| | | |
|----------|--------------------------------|-----------------------------|
| legRF1 | range=[-116.000000,116.000000] | unit=deg : Right fore legJ1 |
| legRF2 | range=[-9.000000,92.000000] | unit=deg : Right fore legJ2 |
| legRF3 | range=[-26.000000,146.000000] | unit=deg : Right fore legJ3 |
| legRH1 | range=[-116.000000,116.000000] | unit=deg : Right hind legJ1 |
| legRH2 | range=[-9.000000,92.000000] | unit=deg : Right hind legJ2 |
| legRH3 | range=[-26.000000,146.000000] | unit=deg : Right hind legJ3 |
| legLF1 | range=[-116.000000,116.000000] | unit=deg : Left fore legJ1 |
| legLF2 | range=[-9.000000,92.000000] | unit=deg : Left fore legJ2 |
| legLF3 | range=[-26.000000,146.000000] | unit=deg : Left fore legJ3 |
| legLH1 | range=[-116.000000,116.000000] | unit=deg : Left hind legJ1 |
| legLH2 | range=[-9.000000,92.000000] | unit=deg : Left hind legJ2 |
| legLH3 | range=[-26.000000,146.000000] | unit=deg : Left hind legJ3 |
| tailPan | range=[-21.000000,21.000000] | unit=deg : Tail tilt |
| tailTilt | range=[-21.000000,21.000000] | unit=deg : Tail pan |
| headTilt | range=[-87.000000,41.000000] | unit=deg : Head tilt |
| headPan | range=[-89.000000,89.000000] | unit=deg : Head pan |
| headRoll | range=[-27.000000,27.000000] | unit=deg : Head roll |
| mouth | range=[-46.000000,-3.000000] | unit=deg : Mouth |

For all joints, you have the following fields:

- `val` : the value of the joint
- `valn` : the normalized value of the joint between 0 and 1
- `load` : the load of the joint. 0 means “loose”, and 1 means “blocked”. Values in between give intermediary results.
- `PGain` : the P gain of the joint
- `IGain` : the I gain of the joint
- `DGain` : the D gain of the joint
- `PShift` : the P shift of the joint
- `IShift` : the I shift of the joint
- `DShift` : the D shift of the joint

4.2.2 Leds, switches, ...

ERS210

| | | |
|--------|---------------------------|-------------------------------------|
| ledEUL | range=[0.000000,1.000000] | unit=bool : Eye light (Upper left) |
| mode | range=[0.000000,1.000000] | unit=bool : Mode indicator |
| ledEUR | range=[0.000000,1.000000] | unit=bool : Eye light (Upper right) |
| earL | range=[0.000000,1.000000] | unit=bool : Left ear |
| earR | range=[0.000000,1.000000] | unit=bool : Right ear |
| ledTB | range=[0.000000,1.000000] | unit=bool : Tail light (Blue) |

| | | |
|--------|---------------------------|--------------------------------------|
| ledTO | range=[0.000000,1.000000] | unit=bool : Tail light (Orange) |
| ledELL | range=[0.000000,1.000000] | unit=bool : Eye light (Lower left) |
| ledEML | range=[0.000000,1.000000] | unit=bool : Eye light (Middle left) |
| ledELR | range=[0.000000,1.000000] | unit=bool : Eye light (Lower right) |
| ledEMR | range=[0.000000,1.000000] | unit=bool : Eye light (Middle right) |

For all these devices, you have the following fields:

- val : the value of the device
- valn : the normalized value of the device

There is a global “led mode” available on ERS7. You can change it via the global variable `robot.ledMode`.

4.2.3 Sensors

| | | |
|--------------|------------------------------|--|
| pawLF | range=[0.000000,1.000000] | unit=bool : Left fore leg,paw sensor |
| pawLH | range=[0.000000,1.000000] | unit=bool : Left hind leg,paw sensor |
| pawRF | range=[0.000000,1.000000] | unit=bool : Right fore leg,paw sensor |
| pawRH | range=[0.000000,1.000000] | unit=bool : Right hind leg,paw sensor |
| backSensor | range=[0.000000,1.000000] | unit=bool : Back sensor |
| chinSensor | range=[0.000000,1.000000] | unit=bool : Chin sensor |
| headSensorB | range=[0.000000,98.000000] | unit=uPa : Head sensor (back) |
| headSensorF | range=[0.000000,98.000000] | unit=uPa : Head sensor (front) |
| psd | range=[0.000000,90.000000] | unit=m : Position Sensing Device |
| thermoSensor | range=[0.000000,60.000000] | unit=C : Thermo sensor |
| accelX | range=[-19.613300,19.613300] | unit=m/s ² : Acceleration sensor (right-left) |
| accelY | range=[-19.613300,19.613300] | unit=m/s ² : Acceleration sensor (front-back) |
| accelZ | range=[-19.613300,19.613300] | unit=m/s ² : Acceleration sensor (up-down) |

For all these devices, you have the following fields:

- val : the value of the device
- valn : the normalized value of the device

4.2.4 Camera

The camera device on Aibo is called `camera`. The available fields are:

- val : the image (binary)
- shutter : the camera shutter speed: 1=SLOW (default), 2=MID, 3=FAST
- gain : the camera gain: 1=LOW, 2=MID, 3=HIGH (default)
- wb : the camera white balance: 1=INDOOR (default), 2=OUTDOOR, 3=FLUO
- format : the camera image format: 0=YCbCr 1=jpeg (default)
- jpegfactor : the jpeg compression factor (0 to 100). Default=80
- resolution : the image resolution: 0:208x160 (default) 1:104x80 2:52x40
- reconstruct : reconstruction of the high resolution image(slow): 0:no (default) 1:yes
- width : image width

- `height` : image height
- `xfov` : camera x FOV (degrees)
- `yfov` : camera y FOV (degrees)
- `ballx` : normalized X position of the red ball in the image (between 0 and 1) or -1 when there is no ball visible.
- `bally` : normalized Y position of the red ball in the image (between 0 and 1) or -1 when there is no ball visible.

4.2.5 Speaker

The speaker device on Aibo is called `speaker`. The available fields are:

- `val` : the sound to play (binary)
- `playing` : equal 1 when there is a sound playing, 0 otherwise
- `remain` : number of milliseconds of sound to play, 0 when the buffer is empty

There is also a method available:

- `play (file)` : plays the wav file *file* which is stored on the root of the memorystick.

4.2.6 Micro

The micro device on Aibo is called `micro`. The available fields are:

- `val` : contains always a buffer of 2048 bytes of the latest sound heard by the robot.

4.3 ERS-220

4.3.1 Motors

The following devices are joints, with the corresponding range indicated:

| | | |
|----------|--------------------------------|-----------------------------|
| legRF1 | range=[-116.000000,116.000000] | unit=deg : Right fore legJ1 |
| legRF2 | range=[-10.000000,92.000000] | unit=deg : Right fore legJ2 |
| legRF3 | range=[-26.000000,146.000000] | unit=deg : Right fore legJ3 |
| legRH1 | range=[-116.000000,116.000000] | unit=deg : Right hind legJ1 |
| legRH2 | range=[-10.000000,92.000000] | unit=deg : Right hind legJ2 |
| legRH3 | range=[-26.000000,146.000000] | unit=deg : Right hind legJ3 |
| legLF1 | range=[-116.000000,116.000000] | unit=deg : Left fore legJ1 |
| legLF2 | range=[-10.000000,92.000000] | unit=deg : Left fore legJ2 |
| legLF3 | range=[-26.000000,146.000000] | unit=deg : Left fore legJ3 |
| legLH1 | range=[-116.000000,116.000000] | unit=deg : Left hind legJ1 |
| legLH2 | range=[-10.000000,92.000000] | unit=deg : Left hind legJ2 |
| legLH3 | range=[-26.000000,146.000000] | unit=deg : Left hind legJ3 |
| headPan | range=[-89.000000,89.000000] | unit=deg : Head pan |
| headRoll | range=[-27.000000,27.000000] | unit=deg : Head roll |
| headTilt | range=[-87.000000,41.000000] | unit=deg : Head tilt |

For all joints, you have the following fields:

- val : the value of the joint
- valn : the normalized value of the joint between 0 and 1
- load : the load of the joint. 0 means “loose”, and 1 means “blocked”. Values in between give intermediary results.
- PGain : the P gain of the joint
- IGain : the I gain of the joint
- DGain : the D gain of the joint
- PShift : the P shift of the joint
- IShift : the I shift of the joint
- DShift : the D shift of the joint

4.3.2 Leds, switches, ...

| | | |
|----------------|---------------------------|--|
| ledTailC | range=[0.000000,1.000000] | unit=bool : Tail light (Center) |
| ledBL | range=[0.000000,1.000000] | unit=bool : Head Face side light (Back l |
| ledTailL | range=[0.000000,1.000000] | unit=bool : Tail light (Left) |
| ledCL | range=[0.000000,1.000000] | unit=bool : Head Face side light (Center |
| ledBR | range=[0.000000,1.000000] | unit=bool : Head Face side light (Back r |
| ledTailR | range=[0.000000,1.000000] | unit=bool : Tail light (Right) |
| ledCR | range=[0.000000,1.000000] | unit=bool : Head Face side light (Center |
| ledFL | range=[0.000000,1.000000] | unit=bool : Head Face side light (Front |
| ledL1 | range=[0.000000,1.000000] | unit=bool : Back multi indic (1st from |
| ledL2 | range=[0.000000,1.000000] | unit=bool : Back multi indic (2nd from |
| ledRetractHead | range=[0.000000,1.000000] | unit=bool : Retractable head light |

| | | |
|---------|---------------------------|---|
| ledL3 | range=[0.000000,1.000000] | unit=bool : Back multi indic (3rd from |
| ledFR | range=[0.000000,1.000000] | unit=bool : Head Face side light (Front |
| ledHead | range=[0.000000,1.000000] | unit=bool : Head indicator |
| ledR1 | range=[0.000000,1.000000] | unit=bool : Back multi indic (1st from |
| ledR2 | range=[0.000000,1.000000] | unit=bool : Back multi indic (2nd from |
| ledR3 | range=[0.000000,1.000000] | unit=bool : Back multi indic (3rd from |
| ledA | range=[0.000000,1.000000] | unit=bool : Face front light A |
| ledB | range=[0.000000,1.000000] | unit=bool : Face front light B |
| ledC | range=[0.000000,1.000000] | unit=bool : Face front light C |

For all these devices, you have the following fields:

- val : the value of the device
- valn : the normalized value of the device

There is a global “led mode” available on ERS7. You can change it via the global variable `robot.ledMode`.

4.3.3 Sensors

| | | |
|--------------|------------------------------|---|
| pawLF | range=[0.000000,1.000000] | unit=bool : Left fore leg,paw sensor |
| pawLH | range=[0.000000,1.000000] | unit=bool : Left hind leg,paw sensor |
| pawRF | range=[0.000000,1.000000] | unit=bool : Right fore leg,paw sensor |
| pawRH | range=[0.000000,1.000000] | unit=bool : Right hind leg,paw sensor |
| thermoSensor | range=[0.000000,60.000000] | unit=uPa : Thermo sensor |
| tailSensorC | range=[0.000000,1.000000] | unit=uPa : Tail sensor (Center from be |
| backSensor | range=[0.000000,99.000000] | unit=uPa : Back sensor |
| tailSensorL | range=[0.000000,1.000000] | unit=uPa : Tail sensor (Left from behi |
| tailSensorR | range=[0.000000,1.000000] | unit=uPa : Tail sensor (Right from behi |
| headSensorB | range=[0.000000,35.000000] | unit=uPa : Head sensor(back) |
| headSensorF | range=[0.000000,60.000000] | unit=uPa : Head sensor(front) |
| faceSensor | range=[0.000000,60.000000] | unit=uPa : Face sensor |
| psd | range=[0.000000,90.000000] | unit=cm : Position Sensing Device |
| accelX | range=[-19.613300,19.613300] | unit=m/s2 : Acceleration sensor(right-l |
| accelY | range=[-19.613300,19.613300] | unit=m/s2 : Acceleration sensor(front-b |
| accelZ | range=[-19.613300,19.613300] | unit=m/s2 : Acceleration sensor(up-down |

For all these devices, you have the following fields:

- val : the value of the device
- valn : the normalized value of the device

4.3.4 Camera

The camera device on Aibo is called `camera`. The available fields are:

- val : the image (binary)
- shutter : the camera shutter speed: 1=SLOW (default), 2=MID, 3=FAST
- gain : the camera gain: 1=LOW, 2=MID, 3=HIGH (default)
- wb : the camera white balance: 1=INDOOR (default), 2=OUTDOOR, 3=FLUO
- format : the camera image format: 0=YCbCr 1=jpeg (default)

- `jpegfactor` : the jpeg compression factor (0 to 100). Default=80
- `resolution` : the image resolution: 0:208x160 (default) 1:104x80 2:52x40
- `reconstruct` : reconstruction of the high resolution image(slow): 0:no (default) 1:yes
- `width` : image width
- `height` : image height
- `xfov` : camera x FOV (degrees)
- `yfov` : camera y FOV (degrees)
- `ballx` : normalized X position of the red ball in the image (between 0 and 1) or -1 when there is no ball visible.
- `bally` : normalized Y position of the red ball in the image (between 0 and 1) or -1 when there is no ball visible.

4.3.5 Speaker

The speaker device on Aibo is called `speaker`. The available fields are:

- `val` : the sound to play (binary)
- `playing` : equal 1 when there is a sound playing, 0 otherwise
- `remain` : number of milliseconds of sound to play, 0 when the buffer is empty

There is also a method available:

- `play (file)` : plays the wav file *file* which is stored on the root of the memorystick.

4.3.6 Micro

The micro device on Aibo is called `micro`. The available fields are:

- `val` : contains always a buffer of 2048 bytes of the latest sound heard by the robot.

Chapter 5

Default URBI.INI

Here is the default URBI.INI file which sets the standard grouping hierarchy for aibo and starts a nice animation (tagged with anim, so that you can stop it with `stop anim`).

```
speaker.play("start.wav");
tps = 4000;

group legRF {legRF1,legRF2,legRF3},
group legLF {legLF1,legLF2,legLF3},
group legRH {legRH1,legRH2,legRH3},
group legLH {legLH1,legLH2,legLH3},
group legs {legRF,legLF,legRH,legLH},
group leg1 {legRF1,legLF1,legRH1,legLH1},
group leg2 {legRF2,legLF2,legRH2,legLH2},
group leg3 {legRF3,legLF3,legRH3,legLH3},

// ERS7
if (global.name == "ERS-7") {
  anim:ledF12.val = 1,
  anim:ledBFW.valn = 0.2 sin:tps ampli:0.5 &
  anim:ledBMW.valn = 0.2 sin:tps ampli:0.5 phase:(pi/3) &
  anim:ledBRW.valn = 0.2 sin:tps ampli:0.5 phase:(2*pi/3),

  group head {neck,headPan,headTilt,mouth},
  group tail {tailPan,tailTilt},
  group ears {earR,earL},
  group robot {legs,head,tail},

  group ledF {ledF1,ledF2,ledF3,ledF4,ledF5,ledF6,ledF7,
              ledF8,ledF9,ledF10,ledF11,ledF12,ledF13,ledF14},
  group ledHead {modeR,modeG,modeB,ledHC,ledHW},
  group ledBW {ledBFW,ledBMW,ledBRW},
  group ledBC {ledBFC,ledBMC,ledBRC},
  group leds {ledF,ledHead,ledBW,ledBC,ledWIFI}
},

//ERS210
if (global.name == "ERS-210") {
  anim: ledEML.val = 1,
```

```

anim: ledEMR.val = 1,
anim: ledTB.val = 0.5 sin:tps ampli:0.6,

group head {headRoll,headPan,headTilt,mouth},
group tail {tailPan,tailTilt},
group robot {legs,head,tail},
group ears {earR,earL},

group ledT {ledTB,ledTO},
group ledE {ledELL,ledEML,ledEUL,ledELR,ledEMR,ledEUR},
group leds {mode,ledT,ledE}
},

```

Chapter 6

Default CLIENT.INI

Here is the default URBI.INI file which plays a sound and start a battery monitor:

```
speaker.play("client.wav");

//Power Monitoring
current_power=inf;
power:at ( current_power - power() >= 0.01 ) {
    current_power=power();
    power:echo "Battery at "+string(current_power*100)+" %"
};
```